Read ME

Team

Preethi R - 2018115076 Indhumathy J - 2018115040 Priyankaa K - 2018115081

List of files

- 1. Camera1.py
- 2. Camera2.py
- 3. Connect.php
- 4. Register.php
- 5. Login.php
- 6. Home.php
- 7. Logout.php
- 8. Contact.html
- 9. test.jpg

Hardware requirements


1. CCTV camera

Software requirements


- 1. Python, PHP, HTML
- 2. Browser
- 3. MySQL database
- 4. Open CV
- 5. Numpy
- 6. Pytesseract
- 7. Imutils
- 8. Pymysql
- 9. Xampp
- 10. PyCharm text editor

Procedure


1. Unzip the source code documents into C:\xampp\htdocs\folder_name



2. Open Xampp control panel and start Apache and MySQL.




3. In the browser open http://localhost/phpmyadmin/index.php




4. Enter the following query to create a database and table.

"CREATE DATABASE SRP"


"CREATE TABLE basic (first_name VARCHAR(20), last_name VARCHAR(20), vehicle_no VARCHAR(10), license_no VARCHAR(20), phone_no int, email VARCHAR(20), password VARCHAR(20), first_time datetime, second_time datetime, speed float, fine int, personID int PRIMARY KEY AUTO INCREMENT)"




5. To create your account, open register.php from localhost.



6. Then login to view your details





- 7. Open pycharm and under file>settings>interpreter install the following packages
 - cv2
 - imutils
 - numpy
 - pytesseract
 - pymysql
 - datetime from _datetime

- 8. Run the camera1.py followed by camera2.py.
- 9. The programs will run the test image and update the timestamp and speed to the database.

